



6320 E Stassney Ln. Phone / 1.800.615.8350
Austin, TX 78744 Email / sales@feniex.com



Quantum Software

How to Program Cruise Mode

Let's take a quick look at how to program cruise using tri color as the example. For starters, I'll select the input that I wish to program cruise on. I'll then select cruise mode and I'll select the brightness I wish to associate with cruise. The majority of customers will most likely select 10%, but you could go up to 100% if you wish to. Once that's done, I'll then select the module that I wish to activate on cruise. I'm only given the choice of the three colors I programmed in the previous step. notice red blue and white appear in this spot while red blue and amber appear in this spot. So in this case I'd like cruise to be red on driver side while I would like cruise to be blue on passenger side. I can also select other colors of course that I wish to associate with cruise if I wish to apply a unique function. And it's as simple as that. Select cruise mode, your intensity, the modules that you wish to activate on on that cruise function. And of course, don't forget to click program device. That concludes how to program cruise mode using the quantum configurator.